



FACEBOOK 360

SPATIAL WORKSTATION USER GUIDE

Release 2.0b1

Feb 28, 2017

Contents

1	Introduction	1
2	Getting Started	2
3	Workflow	3
4	Components	5
5	Using Pro Tools HD	12
6	Using Reaper	17
7	Using Nuendo	20
8	Video Player	23
9	Encoding Assets	25

1 Introduction

1.1 What did you download?

Thanks for downloading the FB360 Spatial Workstation. The suite consists of plugins for DAWs, a VR video player and a cross-platform native engine that makes it easy to design and deliver content for cinematic VR and 360 video projects. For any issues, help or bug reports, go to the [support group](#).

1.2 Binaural Audio

Real-time binaural audio works using HRTFs (or Head Related Transfer Functions). HRTFs work by filtering an audio signal to recreate the complex cues that help us, as humans, localise sounds. The cues are influenced by multiple factors, including the listening environment and the shape of your body, head and ears. In reality, we move our heads and reorient ourselves to localise sounds. We constantly try to bring sounds (or the objects that are creating such sounds) into our line of sight to overcome the ambiguity of spatialisation. Some of the long standing problems of binaural audio can be overcome with head tracking technology, as found on virtual and augmented reality devices. The FB360 Spatial Workstation allows you to position sounds in 3D space within your DAW and then export the mix into a range of formats, including Ambisonics used by popular 360 and VR video platforms and the .tbe format which can be used with the FB360 audio engine within your app to reconstruct a full 3D audio mix based on the user's head orientation.

1.3 Ambisonics and B-format Audio

Ambisonics is a way of describing a full 3D sound field. It uses a number of interdependent audio tracks which can be decoded into various other end-user formats for consumption, e.g. binaural or 5.1, meaning only one Ambisonic recording or mix needs to be made for multiple different use cases. Another major feature is that an Ambisonic mix can be dynamically decoded to incorporate the listener's head rotation. Currently, first order Ambisonics is widely used in spatial audio and this requires four channels of audio, which is often called a B-format. Care should be exercised as there are currently two different common channel ordering and weighting conventions for the B-format:

1. The traditional B-format, as output by many commercial microphones, is defined using the channel ordering and weighting proposed by Furse and Malham (often abbreviated to FuMa). We will refer to this convention as B-format (FuMa).
2. A more extendable convention to the traditional B-format (FuMa) has been proposed, known as ambiX. This is characterised by a different channel ordering and weighting. We will refer to this convention as B-format (ambiX).

Depending on how you recorded your B-format audio you may need to rotate it: see [Rotating the Ambisonic field](#) for details.

Technical details

The Ambisonic field must be defined on a set of 3D axes (X, Y, Z). For a listener at the centre of the field, the B-format convention used is X: front to back, Y: left to right, and Z: up-down. The X, Y, Z Ambisonic channels contain information about the sound field along the corresponding axis (they essentially represent what a figure-of-eight microphone might pick up along that axis). The W channel can be thought of as an omni directional channel.

- B-format (FuMa) lists the channels in order: W, X, Y, Z. The W channel also has a -3 dB gain applied.
- The ambiX convention lists the channels using the Ambisonics Channel Number (ACN) ordering: W, Y, Z, X. The channels also use SN3D normalisation (which for first order Ambisonics simply means that the four channels have a uniform gain normalisation).

1.4 Room Modelling

A majority of the binaural solutions only take into account HRTF measurements made in an anechoic chamber. In reality, we listen to sounds in live environments that alter our sense of localisation. Real-time room modelling, with binaurally spatialised reflections can overcome this. A full real-time room modelling solution can be a CPU intensive process, but FB360 takes the best of both worlds. The room modelling algorithm in FB360 recreates only the reflections that are essential for a convincing 3D audio experience. The room modelling algorithm in FB360 generates the first few orders of reflections inside a simple room model. This helps greatly with the externalisation of sound sources and also improves some common binaural rendering problems such as front/back confusion and elevation perception.

You can control the level of these reflections as well as the reflection order (i.e. the number of individual reflections allowed in one reflection path around a room) using the sliders on the Spatialiser plugin. The size of the room being modelled is controlled globally in the Control plugin. These early reflections can be used effectively with any of your favourite reverberation plugins without any problems. Adding a small pre-delay to the reverb system (30-60ms) allows the early reflections to stand out and greatly enhance the spatialisation effect.

2 Getting Started

2.1 Requirements

- Pro Tools HD 10.3.5+ (including 11 and 12) or a VST based DAW such as Reaper or Nuendo
- macOS 10.7+ or Windows 7+ 64 bit
- A HMD is recommended but not compulsory. The following headsets are supported:
 - macOS: Oculus Rift DK1, Oculus Rift DK2
 - Windows: Oculus Rift, HTC Vive

2.2 Setup (macOS)

1. Run the FB360 Spatial Workstation installer (SpatialWorkstation_2.0b1_OSX.mpkg)
2. The following user files are installed, depending on your choices during the installation process:
 - (a) AAX Plugins in Mac HD/Library/Application Support/Avid/Audio/Plug-Ins/
 - (b) VST 2.x Plugins in Mac HD/Library/Audio/Plug-Ins/Audio/VST
 - (c) VST 3 Plugins in Mac HD/Library/Audio/Plug-Ins/Audio/VST3
 - (d) VR Video Player in Applications/FB360 Spatial Workstation/Video Player
 - (e) Encoder app in Applications/FB360 Spatial Workstation/Encoder
 - (f) A Reaper template/example project in Applications/FB360 Spatial Workstation/Reaper
 - (g) A Nuendo example project in Applications/FB360 Spatial Workstation/Nuendo
 - (h) A Pro Tools HD example project in Applications/FB360 Spatial Workstation/Pro Tools HD

(i) Pro Tools HD template project and I/O settings in ~/Documents/Pro Tools

(j) A copy of this document in Applications/FB360 Spatial Workstation

For VST based DAWs, please consult your DAW documentation for information on setting plugin search paths

2.3 Setup (Windows)

1. Run the FB360 Spatial Workstation installer (SpatialWorkstation_2.0b1_Win64.exe)
2. The following user files are installed, depending on your choices during the installation process:
 - (a) AAX Plugins in C:\Program Files\Common Files\Avid\Audio\Plug-Ins
 - (b) VST3 Plugins in C:\Program Files\Common Files\VST3
 - (c) VR Video Player in C:\Program Files\FB360 Spatial Workstation\Video Player
 - (d) Encoder app in C:\Program Files\FB360 Spatial Workstation\Encoder
 - (e) A Reaper template/example project in C:\Program Files\FB360 Spatial Workstation\Reaper
 - (f) A Nuendo example project in C:\Program Files\FB360 Spatial Workstation\Nuendo
 - (g) A Pro Tools HD example project in C:\Program Files\FB360 Spatial Workstation\Pro Tools HD
 - (h) Pro Tools HD template project and I/O settings in ~/Documents\Pro Tools
 - (i) A copy of this document in C:\Program Files\FB360 Spatial Workstation

Working With The Tools

It is recommended that you read the information in Workflow before setting up your DAW.

For setting up a project in Pro Tools HD, see Using Pro Tools HD, for Reaper, see Using Reaper and Nuendo, see Using Nuendo.


3 Workflow

The FB360 Spatial Workstation is divided into five major components:

1. FB360 Spatialiser plugin
This plugin is meant to be instantiated on every audio channel. You can think of it as an advanced panner that helps you position audio in 3D space with binaural and room simulation algorithms. Behind the scenes, the panner plugin codes the audio into a format with metadata that is then used to construct the full mix.
2. FB360 Control plugin
This plugin should be instantiated on an aux channel. Ensure only one instance is present in your project. All tracks processed with the Spatialiser plugin must be routed to this auxiliary channel. The Control plugin also facilitates communication with the VR Video Player and controls parameters for room modelling.
3. VR Video Player
The player is a standalone app that communicates with the DAW to ensure good synchronisation with your project. This enables you to mix directly to the VR video while previewing and navigating the video in 360 degrees, either on your desktop or with a head-mounted display.
4. FB360 Encoder
The encoder converts the mix from your DAW into a variety of formats that can be deployed with the VR app, including the .tbe format that can be decoded with the FB360 Audio Engine to achieve high quality spatial audio.
5. FB360 Audio Engine
The audio engine must be integrated in the VR app. The mix designed in the DAW is reconstructed binaurally by taking head-tracking information from the VR device into account. The audio engine is not included with the Spatial Workstation.

An extra utility plugin called the FB360 Converter plugin can also be used to rotate a spatial mix in your DAW. This plugin must be instantiated in the signal chain after the Spatialiser plugin but before the Control plugin.

The workflow for mixing and delivering content can be divided into three major stages, as illustrated in the image below.



3.1 Design

The design stage is where you as a sound designer and mixer would spend most of your time. You will be using the FB360 Spatialiser and Control plugins in conjunction with the VR Player to mix in binaural in realtime. The tools have been developed to do all the heavy lifting behind the scenes so that you can focus on designing and delivering great content to a deadline.

3.2 Delivery


This is for the final mastering and delivery of content. The mix from the DAW is encoded into a format that the FB360 audio engine uses to reconstruct a binaural mix in real-time on the target device. All audio and metadata is compressed into a single file format that is designed specifically for mobile and desktop devices to ensure low CPU and memory usage. Alternatively, you can deliver your mix into other formats supported by 360 video and VR platforms. See Encoding Assets.

3.3 Playback

Depending on the output format, your mix can be deployed to popular 360 video and VR platforms or with a VR app using the FB360 Audio Engine integrated. The FB360 Audio Engine is cross-platform and works with both native apps and game engines.

4 Components

4.1 FB360 Spatialiser



The FB360 Spatialiser plugin replaces the conventional DAW panner to give you full 3D positioning, distance attenuation and room modelling parameters. It must be the **last** plugin inserted on the audio channel. All audio processing (such as compression and equalisation) must happen **before** it. All channels with the Spatialiser plugin must be routed to an aux channel which has the FB360 Control plugin instantiated on it.

Parameters

- Input: The channels or format used for processing. In Pro Tools, the available options depend on the number of channels supported by the track (e.g. a stereo track will let you choose Left, Right or Mixdown but you cannot select other options which require a higher channel count).
 - Left: The left channel is used for processing
 - Right: The right channel is used for processing
 - Mixdown: A mono-mixdown of both channels is used for processing
 - B-Format (FuMa): For processing pre-recorded 4 channel, 1st order Ambisonics material in the Furse/Malham B-format. This is the channel configuration output by Soundfield microphones. See Ambisonics and B-format Audio for more information.
 - Source Roll: (visible only with B-Format input) Tilt the B-Format recording (like tilting your head from side to side).
 - Source Pitch: (visible only with B-Format input) Rotate the B-Format recording in the vertical plane or up-down. A positive value is up, while a negative value is down.
 - Source Yaw: (visible only with B-Format input) Rotate the B-Format recording in the horizontal plane or left-right. A positive value is right, while a negative value is left.
 - Envelopment: (visible only with B-Format input) Control the diffuse field of the sound.

- B-format (ambiX): For processing pre-recorded 4 channel, 1st order Ambisonics material in the ambiX format. This format is output by the Zoom H2n recorder in spatial audio mode, for example. See for more information.
 - Source Roll: (visible only with B-Format input) Tilt the B-Format recording (like tilting your head from side to side).
 - Source Pitch: (visible only with B-Format input) Rotate the B-Format recording in the vertical plane or up-down. A positive value is up, while a negative value is down.
 - Source Yaw: (visible only with B-Format input) Rotate the B-Format recording in the horizontal plane or left-right. A positive value is right, while a negative value is left.
 - Envelopment: (visible only with B-Format input) Control the diffuse field of the sound.
- Stereo: For positioning both channels of a stereo file independently. All channels are used for processing.
- 4.0: For positioning 4 channels of a quad file independently. All channels are used for processing.
- 5.0: For positioning 5 channels of a 5.0 file independently. All channels are used for processing.
- 6.0: For positioning 6 channels of a 6.0 file independently. All channels are used for processing.
- 7.0: For positioning 7 channels of a 7.0 file independently. All channels are used for processing.
- Azimuth: The position of the sound on the horizontal plane. 0 degrees is when the sound source is directly in front of the listener, 90 degrees is hard-right, -90 is hard-left and +/-180 is directly behind
- Elevation: The position of the sound on the vertical plane. 0 degrees is when the sound source is directly in front of the listener, 90 degrees is directly above and -90 is below
- Distance: The distance of the sound source from the listener in metres. Room modelling and distance attenuation parameters are affected by this value.
- Spread: The width or spread of the sound in space. A value of 0.1 results in the sound being treated as a point source. A value greater than 0.1 would create a diffused sound that is spread out in space and can also give the impression of a sound being closer to the listener.
- Attenuation: Enable or disable distance based attenuation of the sound
 - Minimum Distance: The distance value after which the amplitude attenuation starts
 - Maximum Distance: The distance value after which the amplitude attenuation stops
 - Factor: The attenuation curve. A value of 1 is a 6dB drop every time the distance is doubled (this is how most sounds work in the 'real' world). A value greater than 1 results in a steeper rolloff.
- Doppler: Toggle Doppler effect. This also enables delayed time of flight, i.e, the sound is delayed based on its distance from the listener. This can greatly improve the localisation quality if room modelling is enabled
 - Doppler Level: Intensity of the doppler effect.
- Room: Enable or disable room modelling. This can greatly enhance the spatialisation effect and quality. See for more information. The room parameters can be controlled through the FB360 Control plugin.
 - Reflection Order: The number of individual reflections allowed in one reflection path around a room. A higher value results in more reflections.
 - Reflection Level: The level of the reflections.
- Panners: The Spatialiser includes an equirect video panner and a 2D (top-down view) panner.
 - Equirect Panner: The equirectangular video panner displays a video frames from the FB360 Video Player. Any video that is loaded into the FB360 Video Player is automatically displayed within the panner. The horizontal axis of the panner maps azimuth, while the vertical axis maps elevation.
 - 2D Panner: The interface can be used to position sounds on a 2D map with a top-down view. The panner is linked to the Azimuth and Distance sliders.
- Arrange: Arranges the channels into a speaker configuration determined by the Input setting
- Channel Tabs: Organised on the left-hand side of the plugin these contain the parameters for each channel. Clicking on a dot in the panner interface will open up the corresponding channel's tab.

Panning

The Spatialiser plugin includes an equirect video panner (top-left of the plugin) and a 2D panner (bottom-left of the plugin). Both panners can be used simultaneously to accurately position sounds in 3D space.

The equirect panner mirrors what is displayed in the FB360 Video Player. When a video is loaded in the FB360 Video Player, it will be automatically shown up in the equirect panner.

Typically most 360 videos are stored in an equirectangular projection (similar to how panoramic photos are saved). This is a “flattened” projection of a 360 video where typically the horizontal axis maps to azimuth and the vertical axis maps to elevation, with the centre of the scene at the centre of the equirect display.

The 2D panner on the other hand shows a top-down view of the scene. While the equirect panner does not show distance, the 2D panner can be used to automate distance effects. The centre of the 2D panner is where the camera is in the scene.

Toolbar And Key Commands

The toolbar to the right of the equirect panner has the following options:

- **Toggle Size:** The size of the plugin can be toggled to show a larger view. This is useful

for more precise panning. Key Command: S.

- **Opacity:** The equirect panner draws a darkened overlay of the video to help make the sound objects more visible. The opacity of this overlay can be controlled with the Opacity slider.

- **Grid:** The grid overlay can be toggled on and off. Key Command: G.

The toolbar to the right of the 2D panner has the following options:

- **Zoom In/Out:** The top-down view can be thought of as a map. The zoom buttons can be used to zoom in and out.

- **Grid:** The grid overlay can be toggled on and off. Key Command: G.

- **Arrange:** When working with multichannel material, the Arrange button can be used to arrange the sound sources as virtual speakers.

Rotating the Ambisonic field

When an Ambisonic input format is selected, the FB360 Spatialiser plugin include sliders to re-orient an Ambisonic recording. For example, if the default perspective of the 360 degree video (i.e, the perspective with which the video starts) does not match the recorded sound field (if the microphone was positioned differently on set, for example), the pitch-yaw-roll sliders can be used to re-orient the sound field. In most cases only the yaw (rotation on the horizontal plane in the left or right direction) and pitch (rotation on the vertical plane or up-down direction) sliders would be required to re-orient the recording.

Using Multiple Input Channels

You can use the FB360 Spatialiser to position each channel of a multichannel track independently. This can be used for playing back a multichannel mix or using a multichannel reverb by inserting the Spatialiser plugin on an aux channel.


1. Set up a track with the following settings. The routing of multichannel audio behaves differently depending on your DAW:
 - **Pro Tools:** make sure the number of track channels matches the audio file you wish to use (e.g. 5.0 track for 5.0 audio file)
 - **Reaper:** set the number channels for the track to 8, regardless of the number of channels in your input audio
 - **Nuendo:** set the track channel configuration to 7.1, regardless of the number of channels in your input audio
2. Set the Input in the FB360 Spatialiser plugin to the appropriate number of channels for your audio file

3. Import your multichannel recording onto the track
4. You can position the individual channels by dragging the numbered dots in the panner or by using the parameters within the corresponding tab on the left
5. Click Arrange to automatically position the channels into a speaker configuration as determined by the Input setting

4.2 FB360 Converter

Occasions may arise where a spatial mix or sub-mix needs to rotate to follow what is happening in a scene, or perhaps an 8 channel spatial mix already exists but is incorrectly oriented relative to the video and needs to be corrected. The Converter plugin is a simple utility which can be inserted between the FB360 Spatialiser plugin and the FB360 Control plugin to allow yaw rotation of the 8 channel FB360 Spatialiser output. Input to the FB360 Converter plugin is the 8 channel spatial audio and the output is the 8 channel spatial audio rotated by the specified number of degrees. You can locate the plugin in various places in the signal chain, or a combination thereof:

- on a single DAW track after the FB360 Spatialiser plugin in order to rotate all sources contained on that track (e.g. to rotate a full 5.1 mix without having to automate each speaker source separately);
- on an 8 channel bus receiving the output from multiple FB360 Spatialiser plugin tracks. This would rotate the spatial mix for all of these tracks;
- on the same track as the FB360 Control plugin (must be located before the FB360 Control plugin) to rotate the entire spatial mix.




Parameters

- Yaw Rotation: Set the number of degrees to rotate the spatial mix input by.

The Yaw Rotation parameter in the FB360 Converter plugin can be automated and controlled via a control surface.

4.3 FB360 Control



The FB360 Control plugin must be instantiated on an aux channel that receives audio from all the other spatialised channels in your project. Make sure you have only one instance of the plugin in your project. All audio processing (such as mastering, compression and equalisation) **must** be applied to the signal before it reaches the plugin.

Note that whilst the room size is controlled globally here from the control plugin, the room modelling reflections are mixed into the 8 channel output from the spatialiser plugin and thus exist in the 8 channel export mix, along with any other effects applied before the Spatialiser plugin. The focus and listener orientation controls are provided for mixing and previewing your audio and do not get applied to the 8 channel export mix: focus and listener orientation are applied in real time during video playback.

Parameters


- Room
 - Room Width: A global setting that changes the width of the room in metres. All sounds that have Room enabled in the FB360 Spatialiser will be affected by this.
 - Room Length: A global setting that changes the length of the room in metres. All sounds that have Room enabled in the FB360 Spatialiser will be affected by this.
 - Room Height: A global setting that changes the height of the room in metres. All sounds that have Room enabled in the FB360 Spatialiser will be affected by this.
 - Room Amp: Amplitude of early reflections in the room
 - Room HF: High frequency absorption within the room. 1 is maximum high frequencies.
- Focus: **Focus effects are not baked into the mix. These parameters can be controlled from your app in real-time using the FB360 Audio Engine.**
 - Mix Focus: If enabled, a portion of the mix will be focused on
 - Follow Head: If enabled, the focus orientation will follow the the listener's gaze
 - Focus Azimuth, Elevation: The orientation of the focus, if Follow Head is disabled. These values are relative to the listener point of view
 - Focus Size: Angle controlling the size of the area included within the focus
 - Off-focus Level: Attenuation level of the mix when not within the focus area
- Listener
 - Get From Video: If enabled, the listener's orientation is automatically queried from the VR Video Player
 - Listener Roll, Pitch, Yaw: The orientation of the listener in 3D space. These values are automatable if Get From Video is disabled.
- Misc
 - Send Timecode: If enabled, the timecode from the DAW session is sent to the VR Video Player
 - Frame Delay: Creates a delay for the VR Video Player in relation to the DAW
 - Decode Binaural: If enabled, the mix is decoded to binaural.

Using Focus Control

The focus effect is meant to be used in real-time within your VR application. The parameters available in the Control plugin are only for preview. To get the focus control working within your VR app:

1. Use the FB360 audio engine in your app and follow the instructions provided with the engine
2. Specify the value of the Focus Size and Off-focus Level For Engine (displayed in the control plugin) in the FB360 audio engine API

4.4 VR Video Player



The Video Player is installed in Applications/FB360 Spatial Workstation/Video Player on macOS and C:\Program Files\FB360 Spatial Workstation/Video Player on Windows. Read [Opening A Video](#) and [Video Format And Codec](#) for more information on setting up the player.

The Video Player can be used in either Slave or Standalone mode.

Slave Mode

Slave mode synchronises video playback with your DAW.

- Load or drop video file: Browse for or drop the video file that needs to be opened
- Select Format
 - Mono: Non-stereoscopic video. This is usually a video that has a single display
 - Over-under: Stereoscopic video, where the video for the left eye is displayed in the top-half and the video for the right eye is displayed in the bottom-half
 - Side-by-side: Stereoscopic video, where the video for the left eye is displayed in the left-half and the video for the right eye is displayed in the right-half
- Display Mode
 - Desktop: The video will be played back in a format that can be viewed on a regular computer display
 - VR: The video will be displayed in a format that is compatible with Oculus Rift DK1/DK2 on macOS or Oculus Rift/HTC Vive on Windows
- Connect to DAW: The computer/DAW the video player is currently connected to. The Video Player optionally can be run on a computer that is different from the one hosting the DAW.
- Open: Opens the video in a new window. The player by default works as a slave and the video will not playback until it receives timecode from the DAW.

Remote DAW Connection

The Video Player and the Control plugin use Bonjour to easily establish a connection whether they are on the same host or different hosts on the same network, even hosts using different operating systems. For example, the Video Player can be run on a Windows host with a VR headset, and the DAW can run on a macOS host.

Each detected host with a Control plugin will be listed in the “Connect to DAW” drop-down. The network interface is displayed in parentheses; for acceptable video latency ensure that you use a wired Ethernet connection, not a wireless connection.

If the expected host does not show up in the drop-down, here are some troubleshooting steps:

- Ensure that the DAW is in fact running with the Control plugin loaded.
- Ensure that the hosts are on the same local area network.
- Ensure that the firewall on both hosts is configured to allow network traffic on at least UDP ports 6100, 5125, and 5353. (If in doubt, temporarily disable the firewalls entirely.)
- On Windows, the Bonjour service is installed by the Spatial Workstation installer. If you opted out, or you or your administrator has since disabled that service, you will need to reenable or reinstall it. You may reinstall the Spatial Workstation, or download and install [Bonjour Print Services for Windows from Apple](#).

Standalone Mode

Standalone mode is independent of a DAW and is to preview an encoded .tbe file with a video.

- Load or drop video file: Browse for the video file that needs to be opened
- Load or drop .tbe file: Browse for the .tbe file that needs to be opened
- Video Format
 - Mono: Non-stereoscopic video. This is usually a video that has a single display
 - Over-under: Stereoscopic video, where the video for the left eye is displayed in the top-half and the video for the right eye is displayed in the bottom-half
 - Side-by-side: Stereoscopic video, where the video for the left eye is displayed in the left-half and the video for the right eye is displayed in the right-half
- Display Mode
 - Desktop: The video will be played back in a format that can be viewed on a regular computer display
 - VR: The video will be displayed in a format that is compatible with Oculus Rift DK1/DK2 on macOS or Oculus Rift/HTC Vive on Windows
- Open: Opens the video in a new window.

5 Using Pro Tools HD

An example Pro Tools HD project and template are automatically installed on your computer. The example project is located in the installation folder, along with a backup copy of the Pro Tools HD template and I/O settings. Use the example project to familiarise yourself with the FB360 Spatial Workstation.

5.1 Creating A New Project

To create a new project with the provided template and I/O options:

Pro Tools 12

1. Open Pro Tools HD
2. Create a new project
3. Select Create From Template
4. Choose Post-Production from the Template Group drop-down menu
5. Select FB360 3D Audio from the list of options
6. Set the sample rate and bit depth of your session (see for information about target sample rates)


7. Select FB360 3D Audio from the I/O Settings drop-down menu
8. Click Create

Pro Tools 11

1. Open Pro Tools HD
2. Create a new project
3. Select Create Session From Template...
4. Choose Post-Production from the drop-down menu
5. Select FB360 3D Audio from the list of options
6. Set the sample rate and bit depth of your session (see for information about target sample rates)
7. Click Ok

Pro Tools 10

1. Open Pro Tools HD
2. Go to File → Open Project and open Mac HD/Applications/FB360 Spatial Workstation/Pro Tools HD/Session Templates/Post Production/FB360 3D Audio.ptxt on macOS or C:/Program Files/FB360 Spatial Workstation/Pro Tools HD/Session Templates/Post Production/FB360 3D Audio.ptxt on Windows
3. Choose your session sample rate and bit depth
4. Pro Tools will now prompt you to save the template as a new session
5. Save your project



5.2 Project Structure

The FB360 Spatialiser plugin accepts mono, stereo or multi-channel inputs and outputs 8 channels of audio. These 8 channels of audio must be routed to the FB360 Control plugin for further processing. Make sure you have only one master channel and instance of the FB360 Control plugin in your project. You can create as many mono, stereo or quad tracks with the FB360 Spatialiser plugin as your project requires. There are no limitations. You can also use the separate FB360 Converter plugin to rotate the 8 channel audio output from the FB360 Spatialiser plugin, or any 8 channel sub-mix before being input to the FB360 Control plugin.

The template project consists of spatialised tracks that have the FB360 Spatialiser plugin inserted and 'normal' stereo audio tracks. The spatialised tracks are meant for full binaural panning and are routed to a channel called 3D Master, while the stereo tracks are meant for head-locked stereo panning and are routed to a channel called Head-locked Master. It is recommended that you stick to this project structure as it makes it easier to export, debug and deliver mixes. Any audio track in your project must either be routed to 3D Master or Head-locked Master.

Mastering

The template project includes two master channels: 3D Master for all 3D elements in the mix and Head-locked Master for all non-spatialised elements in the mix. The 3D Master channel is a master auxiliary channel that receives audio from all FB360 Spatialiser channels. Use it just as you would use a master fader master volume automation, mastering EQ, etc. The Head-locked Master channel functions in a similar way, but receives audio from all head-locked stereo tracks. Your mastering chain would need to be applied separately on both masters.

3D And Head-locked Stereo

It is quite common that some elements in the mix such as the background score or voice overs might not need to be spatialised in 3D or react to head-tracking. The two masters, 3D Master and Head-locked Master facilitate this workflow. **Note: some spatial audio formats do not support head-locked stereo/non-spatialised audio.**

Mixing

For the spatialised tracks, make sure that the FB360 Spatialiser is the last plugin in the chain (except if you use the FB360 Converter plugin, which must be located in the signal chain after the FB360 Spatialiser plugin, but before the FB360 Control plugin). Panning can be controlled and automated through either the sliders or the 2D panner. All parameters in the FB360 Spatialiser plugin can be automated and controlled via a control surface.

Sub-Mixes

You can create sub-mixes by routing audio from FB360 Spatialiser channels to an 8 channel (7.1) aux channel. This aux channel would then need to be routed to 3D Master.

Previewing Your Mix

The audio from the 3D Master aux is routed to the Control Plugin aux which has the FB360 Control plugin instantiated on it. The Control plugin is used for setting global parameters (such as room modelling) and for communicating with the video player. See FB360 Control for more information.

Creating New Tracks

To create a new spatialised or head-locked stereo track, duplicate one of the existing tracks in the project. If you need to manually create and setup a spatialised track:


1. Create a new mono or multichannel track
2. Instantiate the FB360 Spatialiser by going to multichannel plug-in/Soundfield/FB360 Spatialiser in the insert plugin drop-down menu
3. Set the track's output to To 3D Master bus

When using a multichannel audio file make sure the number of track channels matches the number of channels on the audio file.

5.3 Sample Rate Considerations

You can create your Pro Tools HD project with any sample rate of your choice, although, 48000Hz is recommended.

5.4 Ambisonics/B-format



The FB360 Spatialiser plugin can also handle and decode Ambisonics material in either the B-Format (FuMa) or B-format (ambiX) formats. Here's how you get it working:

1. Create a new quad track
2. Insert the FB360 Spatialiser plugin
3. Set the track's output to To 3D Master bus
4. In FB360 Spatialiser, set the Input drop-down menu to B-format (FuMa) or B-format (ambiX) depending on your source material
5. Import your 4 channel B-format recording onto the track
6. The B-format data will automatically be spatialised to binaural by the FB360 Control plugin

For more information about Ambisonics and B-formats see the Ambisonics and B-format Audio section or for information on rotating the B-format recording, see Rotating the Ambisonic field.

5.5 Working With Video

Once you have the video opened and loaded in the VR Video Player, playing back your session in Pro Tools HD should automatically synchronise playback of the video. Pro Tools HD is always master and the video player is slave. Make sure your project or your first frame of action starts at 00:00:00:00. See Opening A Video and Navigating A 360 Video for more information.


5.6 Exporting A Mix

To export your spatialised and head-locked stereo mix stems:

1. Record enable the 3D Stem and Head-locked Stem tracks. Make sure they are muted.
2. Record your session
3. Export the regions in the 3D Stem and Head-locked Stem tracks by selecting the regions and pressing Cmd + Shift + K on your keyboard. Ensure the export format is set to Interleaved.

Both files will now need to be processed and coded before being deployed to the app using the external encoder application. See Encoding Assets.

6 Using Reaper



Open the example Reaper project `SpatialWorkstation.RPP` installed in the FB360 Spatial Workstation installation folder. Go to `File → Save Project As..` in the menu bar. Specify a name and location for your project. It is recommended that you use `SpatialWorkstation.RPP` as a template for all projects that use the Spatial Workstation plugins.

6.1 Project Structure

The project consists of spatialised tracks that have the FB360 Spatialiser plugin inserted and 'normal' stereo audio tracks. The spatialised tracks are meant for full binaural panning and are routed to a channel called `3D MASTER`, while the stereo tracks are meant for head-locked stereo panning and are routed to a channel called `HL MASTER`. It is recommended you stick to this project structure as it makes it easier to export, debug and deliver mixes. Any audio track in your project must either be routed to `3D MASTER` or `HL MASTER`.


The `CONTROL PLUGIN` audio channel is a master auxiliary channel with the FB360 Control plugin inserted. Make sure you have only one master channel and instance of the FB360 Control plugin in your project! No additional plugins should be added to the `CONTROL PLUGIN` channel!

Creating New Tracks

To create a new spatialised or head-locked stereo track, duplicate one of the existing tracks in the project. If you need to manually create and setup a spatialised track:

1. Create a new track
2. In the Mixer view, click on the 'I/O' button
3. Set Track Channels to 8

4. Click on the Add New Send.. drop down menu and select 3D MASTER
5. Under the options for this newly created send, set Audio to Multichannel source → 8 Channels → 1-8.
6. Uncheck/disable the Master/parent send option at the top-left of the window




6.2 Mastering

The template project includes two master channels: 3D MASTER for all 3D elements in the mix and HL MASTER for all non-spatialised elements in the mix. The 3D MASTER channel is a master auxiliary channel that receives audio from all FB360 Spatialiser channels. Use it just as you would use a master fader master volume automation, mastering EQ, etc. The HL MASTER channel functions in a similar way, but receives audio from all head-locked stereo. Your mastering chain would need to be applied separately on both masters.

6.3 Mixing

For the spatialised tracks, make sure that the FB360 Spatialiser is the last plugin in the chain (except if you use the FB360 Converter plugin, which must be located in the signal chain after the FB360 Spatialiser plugin, but before the FB360 Control plugin). Panning can be controlled and automated through either the sliders or the 2D panner. All parameters in the FB360 Spatialiser plugin can be automated and controlled via a control surface.

6.4 Ambisonics/B-Format



The FB360 Spatialiser plugin can also handle and decode Ambisonics material in either the B-Format (FuMa) or B-format (ambiX) formats. Here's how you get it working:

1. Create a new track with the settings specified in or duplicate an existing track (ensure the track has 8 channels, even though only four channels will have audio)
2. Insert an instance of the FB360 Spatialiser plugin, if one isn't present already
3. In FB360 Spatialiser, set the Input drop-down menu to B-format (FuMa) or B-format (ambiX) depending on your source material
4. Import your 4 channel B-format recording into the track
5. The B-format data will automatically be spatialised to binaural by the FB360 Control plugin

For more information about Ambisonics and B-formats see the Ambisonics and B-format Audio section or for information on rotating the B-format recording, see Rotating the Ambisonic field.

6.5 Working With Video

Once you have the video opened and loaded in the VR Video Player, playing back your session in Reaper should automatically synchronise playback of the video. Reaper is always master and the video player is slave. Make sure your project starts at 00:00:00:00. See Opening A Video and Navigating A 360 Video for more information.

6.6 Exporting/Bouncing A Mix

To export your spatialised mix:

1. Use Reaper's Time Selection to specify the area you would like to bounce. Make sure the selection starts at 00:00:00:00
2. Select the 3D MASTER track (and no other track)
3. Go to File → Render in the menu bar


4. In the Render To File window that shows up, choose Stems (selected tracks) in the Source drop-down menu
5. In the Bounds drop-down menu, choose Time Selection
6. Specify the file name and output directory
7. Under Options, specify 8 in the Channels option
8. Click Render 1 file..

The spatialised mix should now be exported. Next, export the head-locked stereo mix:

1. Select the HL MASTER track (and no other track)
2. Go to File → Render in the menu bar again
3. In the Render To File window that shows up, choose Stems (selected tracks) in the Source drop-down menu
4. In the Bounds drop-down menu, choose Time Selection
5. Specify the file name and output directory
6. Under Options, specify 2 in the Channels option
7. Click Render 1 file..

Both files will now need to be processed and coded before being deployed to the app.

7 Using Nuendo



Open the example Nuendo project `SpatialWorkstation.npr` from the FB360 Spatial Workstation installation folder. Go to File → Save As.. in the menu bar. Specify a name and location for your project. It is recommended that you use `SpatialWorkstation.npr` as a template for all projects that use the Spatial Workstation plugins.

7.1 Project Structure

The project consists of spatialised tracks that have the FB360 Spatialiser plugin inserted and 'normal' stereo audio tracks. The spatialised tracks are meant for full binaural panning and are routed to a channel called 3D MASTER, while the stereo tracks are meant for head-locked stereo panning and are routed to a channel called HL MASTER. It is recommended you stick to this project structure as it makes it easier to export, debug and deliver mixes. Any audio track in your project must either be routed to 3D MASTER or HL MASTER.

The 3D MASTER audio channel is a group track with the FB360 Control plugin inserted. Make sure you have only one 3D group track and instance of the FB360 Control plugin in your project!

Creating New 3D Tracks

To create a new spatialised track, duplicate one of the existing tracks in the project. If you need to manually create and setup a spatialised track:

1. Create a new track by going to Project → Add Track → Audio..
2. Set the configuration of the track to More → 7.1 Cine
3. Specify a track name and click on Add Track
4. Set the output of the track to 3D MASTER

Creating New Head-locked Stereo Tracks


To create a new head-locked stereo track, duplicate one of the existing tracks in the project. If you need to manually create and setup a head-locked stereo track:

1. Create a new track by going to Project → Add Track → Audio..
2. Set the configuration of the track to Stereo
3. Specify a track name and click on Add Track
4. Set the output of the track to HL Master

7.2 Mixing

For the spatialised tracks, make sure that the FB360 Spatialiser is the last plugin in the chain (except if you use the FB360 Converter plugin, which must be located in the signal chain after the FB360 Spatialiser plugin, but before the FB360 Control plugin). Panning can be controlled and automated through either the sliders or the 2D panner. All parameters in the FB360 Spatialiser plugin can be automated and controlled via a control surface.

7.3 Ambisonics/B-Format



The FB360 Spatialiser plugin can also handle and decode Ambisonics material in either the B-Format (FuMa) or B-format (ambiX) formats. Here's how you get it working:

1. Create a new track with the settings specified in or duplicate an existing track
2. Insert an instance of the FB360 Spatialiser plugin, if one isn't present already
3. In FB360 Spatialiser, set the Input drop-down menu to B-format (FuMa) or B-format (ambiX) depending on your source material
4. Import your 4 channel B-format recording into the track
5. The B-format data will automatically be spatialised to binaural by the FB360 Control plugin

For more information about Ambisonics and B-formats see the Ambisonics and B-format Audio section or for information on rotating the B-format recording, see Rotating the Ambisonic field.


7.4 Working With Video

Once you have the video opened and loaded in the VR Video Player, playing back your session in Nuendo should automatically synchronise playback of the video. Nuendo is always master and the video player is slave. Make sure your project starts at 00:00:00:00. See Opening A Video and Navigating A 360 Video for more information.

7.5 Exporting/Bouncing A Mix

To export your spatialised mix:

1. Open the FB360 Control plugin. Disable Render Binaural. Minimise the plugin, do not close it.
2. Use Nuendo's Time Selection to specify the area you would like to bounce. Make sure the selection starts at 00:00:00:00
3. Select the 3D MASTER track (and no other track)
4. Go to File → Export → Audio Mixdown
5. Select 3D MASTER from the Channel Selection box
6. Specify the file name and output directory
7. Click Export



The spatialised mix should now be exported. Next, export the optional head-locked stereo mix:

1. Select the HL MASTER track (and no other track)
2. Go to File → Export → Audio Mixdown
3. Select HL MASTER from the Channel Selection box

4. Specify the file name and output directory
5. Click Export

Both files will now need to be processed and coded before being deployed to the app.

8 Video Player

The video player by default works as a slave to the DAW. Once a file is opened and loaded, playback will be controlled from and synchronised to your DAW.

A list of known issues is maintained in the Knowledge Base and can be found [here](#).

8.1 Video Format And Codec

While the video player can load and playback a variety of formats, the following is recommended:


- ProRes HQ: On both macOS and Windows this results in higher quality playback with quick frame-by-frame scrubbing and seeking
- Cineform (Windows Only): On Windows this results in higher quality playback with quick frame-by-frame scrubbing and seeking

Frame-by-frame scrubbing and seeking would be important when you want the video player to synchronise to the timeline selection/playhead position in the DAW when you aren't playing back your session (such as when editing or synchronising edit points). Refer to [this](#) Knowledge Base article for details on the recommended frame rate and resolution.

Encoding With FFmpeg Droplets

On OSX, you can use an Automator droplet with FFmpeg to encode your video files with the recommended settings that work with the video player. On Windows you can use any video encoding software and follow the codec recommendations listed [here](#) in the Knowledge Base.

1. Download the automation droplet file from [here](#).
2. Unzip the archive and place Convert_ProRes.app in a folder on your hard disk
3. Download FFmpeg binaries for OSX from <http://www.ffmpegmac.net/>
4. Unzip the download
5. Copy ffmpeg to the folder that contains Convert_ProRes.app
6. Drag and drop the video you would like to convert over Convert_ProRes.app.



7. A terminal window should open up and show progress

```
Stream #0:0 -> #0:0 (hevc (native) -> prores (native))
Press [q] to stop, [?] for help
frame= 8 fps=0.0 q=0.0 size= 164kB time=00:00:00.06 bitrate=20132.2kbits/
frame= 18 fps= 16 q=0.0 size= 926kB time=00:00:00.33 bitrate=22741.8kbits/
frame= 35 fps= 21 q=0.0 size= 2588kB time=00:00:00.90 bitrate=23536.1kbits/
frame= 54 fps= 24 q=0.0 size= 4446kB time=00:00:01.53 bitrate=23728.9kbits/
frame= 71 fps= 26 q=0.0 size= 6108kB time=00:00:02.10 bitrate=23803.6kbits/
frame= 87 fps= 27 q=0.0 size= 7673kB time=00:00:02.63 bitrate=23844.5kbits/
frame= 105 fps= 28 q=0.0 size= 9405kB time=00:00:03.23 bitrate=23804.7kbits/
frame= 123 fps= 29 q=0.0 size= 11306kB time=00:00:03.83 bitrate=24138.2kbits/
frame= 140 fps= 29 q=0.0 size= 13125kB time=00:00:04.40 bitrate=24411.6kbits/
frame= 158 fps= 30 q=0.0 size= 15050kB time=00:00:05.00 bitrate=24633.6kbits/
frame= 177 fps= 30 q=0.0 size= 17083kB time=00:00:05.63 bitrate=24816.6kbits/
frame= 195 fps= 31 q=0.0 size= 18971kB time=00:00:06.23 bitrate=24907.7kbits/
frame= 213 fps= 31 q=0.0 size= 20614kB time=00:00:06.84 bitrate=24688.3kbits/
frame= 230 fps= 31 q=0.0 size= 22173kB time=00:00:07.40 bitrate=24522.1kbits/
frame= 249 fps= 32 q=0.0 size= 23916kB time=00:00:08.04 bitrate=24363.9kbits/
frame= 266 fps= 32 q=0.0 size= 25475kB time=00:00:08.60 bitrate=24242.0kbits/
frame= 276 fps= 31 q=0.0 size= 26315kB time=00:00:08.94 bitrate=24106.7kbits/
frame= 288 fps= 30 q=0.0 size= 50394kB time=00:00:09.34 bitrate=44187.1kbits/
frame= 298 fps= 30 q=0.0 size= 95369kB time=00:00:09.67 bitrate=80739.4kbits/
frame= 308 fps= 29 q=0.0 size= 140889kB time=00:00:10.01 bitrate=115301.1kbits
frame= 317 fps= 28 q=0.0 size= 181898kB time=00:00:10.31 bitrate=144526.4kbits
/s
```

8. The converted file (named converted_prores.mov) will be placed on your desktop

9. Done!

Encoding With FFmpeg And Command Line

We recommend using FFmpeg (<http://ffmpegmac.net/>) with the settings specified below. FFmpeg is usually used as a command line utility using the Terminal application on a Mac:

- Apple ProRes:

```
ffmpeg -y -probesize 5000000 -i YOUR_INPUT_FILE -vcodec prores -profile:v 3 -qscale:v 11 -an YOUR_
→OUTPUT_FILE.mov
```

- -vcodec Specifies prores as the output codec
- -profile:v 3 ProRes HQ profile
- -qscale:v 11 Sets the quality and file size tradeoff
- -an Disables audio. Removing this option will retain the audio track in the video file (if present)

8.2 Opening A Video

Slave Video Playback

Open the Video Player app from the installation folder. Load the video file, specify the playback options and click Open. For more information about the options, see VR Video Player. If Slave is selected playback will automatically be controlled from your DAW.

Standalone Video Playback

Open the Video Player app from the installation folder. Load the video file and the .tbe file. Select the playback options and click Open.

8.3 Navigating A 360 Video

If VR is selected as the Display Mode, you will need a VR headset connected to your computer. The video will be displayed on the device (provided it is setup correctly) and the information from the head-tracker will automatically

be sent to the video player and the FB360 Control plugin. If you have chosen the Desktop display mode, you can use your keyboard and mouse to navigate the video.

Key Commands

- Left-click and drag your mouse to change orientation (Desktop Mode)
- Use W, A, S or D keys to change orientation. Additionally holding shift increases the rate of rotation (Desktop Mode)
- Use R to reset the camera/listener to the default position (VR and Desktop Mode)

9 Encoding Assets

The Encoder application is installed in Mac HD/Applications/FB360 Spatial Workstation/Encoder on macOS and Mac HD/Applications/FB360 Spatial Workstation/Encoder on Windows. It can be used to convert your mix to a variety of formats or create a file that can be uploaded to Facebook 360.


9.1 Additional Requirements (Windows Only)

The Encoder requires Mp4Box and Python 2.7 installed on your Windows computer.


1. The Python 2.7 installer can be downloaded from [here](#). Follow the instructions with the installer.
2. Mp4Box can be installed using the GPAC installer from [here](#). The GPAC installer includes Mp4Box and other components. Installing the additional components is optional

9.2 Encoding For Facebook 360


1. Open FB360 Encoder




2. For uploads to Facebook, ensure that OUTPUT FORMAT is set to Facebook 360 Video
3. Drop or load the multichannel spatial audio wav file. This is the audio that will rotate and respond when looking around a 360 video. The wav file can be of any sample rate, but is ultimately converted to 48000Hz samples per second
4. Ensure you specify the spatial audio format. It can be one of these five:




- (a) Spatial Workstation 8 Channel: If you have used the Spatial Workstation to design your audio mix, this would be the output of the 3D master from your audio session
 - (b) B-format ambiX 1st order: First order ambisonics with ACN ordering and SN3D normalisation, from any other mix or tool (4 channels)
 - (c) B-format FuMa: First order ambisonics with Furse-Malham ordering, typically the B-format audio from ambisonic microphones (4 channels)
 - (d) B-format ambiX 2nd order: Second order ambisonics with ACN ordering and SN3D normalisation, from any other mix or tool (9 channels)
 - (e) B-format FuMa 2nd order: Second order ambisonics with Furse-Malham ordering, typically the B-format audio from ambisonic microphones (9 channels)
5. Ensure the From Pro Tools checkbox is ticked if the 8 channel spatial audio file is from Pro Tools
 6. Optionally, you can also drop or load a stereo file for head-locked audio. This is audio that will not rotate when looking around a 360 video



7. Drop or load the video file. Ensure that the video is encoded as H.264 within an mp4 container
8. Set the layout for the video file:




- (a) Monoscopic: A monoscopic video, where the same frame will be displayed to both eyes when viewing in 3D
 - (b) Top-Bottom Stereoscopic: A stereoscopic video, where the top half of the video will be displayed to the left eye and the bottom half of the video will be displayed to the right eye when viewing in 3D
 - (c) Left-Right Stereoscopic: A stereoscopic video, where the left half of the video will be displayed to the left eye and the right half of the video will be displayed to the right eye when viewing in 3D
9. For videos encoded in Facebook 360 format, you can optionally enable Focus for the video which will give more prominence to the audio objects in the viewer's field of view and will attenuate objects outside of it:



- Focus: Enables the focus feature
 - Focus Size: The size of the angle of the focus cone in degrees (ranged from 40 to 120)
 - Off-focus Level: The attenuation of objects outside of the focus area in decibels (ranged -24.0 to 0.0)
10. Click the Encode button and save your file
 11. Upload the encoded file to Facebook

9.3 Encoding To Other Formats

The Encoder app can also be used to convert an existing mix from the Spatial Workstation to other formats.



- Facebook 360 Video: Encoding audio and video for Facebook 360, as specified above
- .tbe: Encode the eight channel spatial audio mix from the Spatial Workstation (the output from 3D Master) and head-locked audio for the Facebook 360 Audio Rendering SDK. Note: the video is not used.
- B-format (FuMa): Convert your mix B-format FuMa. Note: the head-locked audio is ignored and the video is not used
- B-format (ambiX): Convert your mix B-format ambiX. Note: the head-locked audio is ignored and the video is not used
- Quad-binaural: Convert your mix to quad-binaural (four binaural mixdowns at 0, 90, 180 and 270 degrees). Note: the head-locked audio is ignored and the video is not used
- YouTube Video (with 1st order ambiX): Encoding audio and video for uploading to either YouTube or Facebook 360. Supports first-order ambiX. For your convenience you can also choose Spatial Workstation 8-channel input which will be converted to first order ambiX, at a loss of quality.

1. Open FB360 Encoder
2. Select the output format
3. Drop or load the 8 channel spatial audio wav file from the Spatial Workstation
4. Ensure the From Pro Tools checkbox is ticked if the 8 channel spatial audio file is from Pro Tools
5. Click the Encode button and save your file

